

## Product datasheet for AM00702BT-L

# Tfrc Rat Monoclonal Antibody [Clone ID: R17217.1.4]

**Product data:** 

**Product Type:** Primary Antibodies

Clone Name: R17217.1.4

Applications: FC

**Recommended Dilution:** Flow Cytometry.

Reactivity: Mouse
Host: Rat
Isotype: IgG2a

Clonality: Monoclonal

**Specificity:** Anti-mouse CD71 antigen monoclonal antibody reacts with the transferrin receptor (CD71).

The expression of CD71 is up-regulated after B cell or T cell activation.

Formulation: PBS containing 0.09% sodium azide (NaN3) as preservative and EIA grade BSA as a stabilizing

protein Label: Biotin

State: Liquid purified Ig fraction

Concentration: lot specific
Conjugation: Biotin

Storage: Store the antibody undiluted at 2-8°C for one month or (in aliquots) at -20°C for longer.

Avoid repeated freezing and thawing.

**Stability:** Shelf life: one year from despatch.

**Gene Name:** transferrin receptor

Database Link: Entrez Gene 22042 Mouse

Q62351

**Synonyms:** TfR1, p90, Transferrin receptor protein 1



**OriGene Technologies, Inc.** 9620 Medical Center Drive, Ste 200

CN: techsupport@origene.cn

Rockville, MD 20850, US Phone: +1-888-267-4436 https://www.origene.com techsupport@origene.com EU: info-de@origene.com



Note:

### Protocol: FLOW CYTOMETRY ANALYSIS:

### Method:

- 1. Prepare a cell suspension in media A. For cell preparations, deplete the red blood cell population with Lympholyte®-M cell separation medium.
- 2. Wash 2 times.
- 3. Resuspend the cells to a concentration of 2x10e7 cells/ml in media A. Add  $50 \mu l$  of this suspension to each tube (each tube will then contain  $1 \times 10e6$  cells, representing 1 test).
- 4. To each tube, add  $\sim$ 1.0 µg of this antibody per 10e6 cells.
- 5. Vortex the tubes to ensure thorough mixing of antibody and cells.
- 6. Incubate the tubes for 30 minutes at 4°C.
- 7. Wash 2 times at 4°C.
- 8. Add 100 µl of secondary antibody (Streptavidin-FITC) at a 1/500 dilution.
- 9. Incubate tubes at 4°C for 30 60 minutes (It is recommended that tubes are protected from light since most fluorochromes are light sensitive).
- 10. Wash 2 times at 4°C.
- 11. Resuspend the cell pellet in 50 µl ice cold media B.
- 12. Transfer to suitable tubes for flow cytometric analysis containing 15  $\mu$ l of propidium iodide at 0.5 mg/ml in PBS. This stains dead cells by intercalating in DNA.

#### Media:

- A. Phosphate buffered saline (pH 7.2) + 5% normal serum of host species + sodium azide (100  $\mu$ l of 2M sodium azide in 100 mls).
- B. Phosphate buffered saline (pH 7.2) + 0.5% Bovine serum albumin + sodium azide (100  $\mu$ l of 2M sodium azide in 100 mls).

### **Results:**

Tissue Distribution by Flow Cytometry Analysis:

(Representative Histogram)

Mouse Strain: Mouse Hybridomas

Cell Concentration: 1x10e6 cells per test

Antibody Concentration Used: 1.0 µg/10e6 cells

<u>Isotypic Control:</u> Biotin Rat IgG2a